

-----[example.c]-----

```

1  /* CS3650 -- handout w04b
2   * compile and run this code with:
3   * $ gcc -g -Wall -o example example.c
4   * $ ./example
5   *
6   * examine its assembly with:
7   * $ gcc -O0 -S example.c
8   * $ [editor] example.s
9   */
10
11 #include <stdio.h>
12 #include <stdint.h>
13
14 uint64_t f(uint64_t* ptr);
15 uint64_t g(uint64_t a);
16 uint64_t* q;
17
18 int main(void)
19 {
20     uint64_t x = 0;
21     uint64_t arg = 8;
22
23     x = f(&arg);
24
25     printf("x: %lu\n", x);
26     printf("dereference q: %lu\n", *q);
27
28     return 0;
29 }
30
31 uint64_t f(uint64_t* ptr)
32 {
33     uint64_t x = 0;
34     x = g(*ptr);
35     return x + 1;
36 }
37
38 uint64_t g(uint64_t a)
39 {
40     uint64_t x = 2*a;
41     q = &x; // <-- THIS IS AN ERROR (AKA BUG)
42     return x;
43 }
```

-----[as.txt (x86)]-----

```

1  2. A look at the assembly...
2
3  To see the assembly code that the C compiler (gcc) produces:
4  $ gcc -O0 -S example.c
5  (then look at example.s)
6  NOTE: what we show below is not exactly what gcc produces. We have
7  simplified, omitted, and modified certain things.
8
9  main:
10    pushq %rbp          # prologue: store caller's frame pointer
11    movq %rsp, %rbp      # prologue: set frame pointer for new frame
12
13    subq $16, %rsp       # make stack space
14
15    movq $0, -8(%rbp)    # x = 0 (x lives at address rbp - 8)
16    movq $8, -16(%rbp)   # arg = 8 (arg lives at address rbp - 16)
17
18    leaq -16(%rbp), %rdi # load the address of (rbp-16) into %rdi
19    # this implements "get ready to pass (&arg)
20    # to f"
21
22    call f               # invoke f
23
24    movq %rax, -8(%rbp)  # x = (return value of f)
25
26    # eliding the rest of main()
27
28 f:
29    pushq %rbp          # prologue: store caller's frame pointer
30    movq %rsp, %rbp      # prologue: set frame pointer for new frame
31
32    subq $32, %rsp       # make stack space
33    movq %rdi, -24(%rbp) # Move ptr to the stack
34    # (ptr now lives at rbp - 24)
35    movq $0, -8(%rbp)    # x = 0 (x's address is rbp - 8)
36
37    movq -24(%rbp), %r8  # move 'ptr' to %r8
38    movq (%r8), %r9      # dereference 'ptr' and save value to %r9
39    movq %r9, %rdi        # Move the value of *ptr to rdi,
40    # so we can call g
41
42    call g               # invoke g
43
44    movq %rax, -8(%rbp)  # x = (return value of g)
45    movq -8(%rbp), %r10  # compute x + 1, part I
46    addq $1, %r10         # compute x + 1, part II
47    movq %r10, %rax      # Get ready to return x + 1
48
49    movq %rbp, %rsp       # epilogue: undo stack frame
50    popq %rbp            # epilogue: restore frame pointer from caller
51    ret                  # return
52
53 g:
54    pushq %rbp          # prologue: store caller's frame pointer
55    movq %rsp, %rbp      # prologue: set frame pointer for new frame
56
57    ....
58
59    movq %rbp, %rsp       # epilogue: undo stack frame
60    popq %rbp            # epilogue: restore frame pointer from caller
61    ret                  # return
```

Crash course of x86-64 assembly

* move instruction:

syntax:
movq PLACE1, PLACE2

means "move 64-bit quantity from PLACE1 to PLACE2". the places are usually registers or memory addresses, and can also be immediates (constants).

Other useful instructions:

* pushq %rax equivalent to:
[subq \$8, %rsp
 movq %rax, (%rsp)]

"(%rsp)" means getting the value in %rsp,
which is a memory address here (e.g., "0x12345")

* popq %rax [movq (%rsp), %rax
 addq \$8, %rsp]

* call 0x12345 [pushq %rip
 movq \$0x12345, %rip]

"\$0x12345" represents a constant (notice the "\$" symbol).
Q: what does the instruction mean without "\$"?
(i.e., move 0x12345, %rip)

* ret [popq %rip]